

Installation Procedures for installing and running IVoDS

1. You need to be logged on as administrator or use an account that has administrator privileges to perform the following tasks.
2. Using IE 5.0 or higher, download the CUWEB plug-in from [CUseeMe Web Installation Center - Version 2.0.0](#)
3. If you have a previous version of IvoDS installed, please uninstall. Go to **C**ontrol Panel> **A**dd/Remove Programs> **S**elect the **IvoDS Self-Extraction program**.
4. **O**pen the [ivods.exe](#) file. (You will have to enter a one-time user name and password obtained from the HOSC Help Desk at 256-544-5066.)
5. Once the ivods.exe completes, you should have seen 2 dialog messages stating "DLLRegisterServer in ivods.dll succeeded" and "DLLRegisterServer in wrtpnet.dll succeeded". If these do not succeed, please notify the HOSC help desk at 256-544-5066 or email hsd@ums.msfc.nasa.gov and receive further instructions. You should now see an IvoDS icon on your desktop. This will be used to launch IVoDS.
6. Make sure that JAVA is enabled before you run IVoDS.
(note: Java is not enabled by default). The following settings must be enabled.
 - **Select Tools-> Internet Options from the IE menubar.**
 - **Select the Advanced Tab**
 - **Find the Java VM section; select all three of the options.**
 - **Scroll to the Security section on this tab, select the check box next to "Empty Temporary Internet Folder when Browser is closed"**
 - **Select the Security Tab**
 - **Select the "Internet" icon.** ←
 - **Adjust the slider bar at the bottom of the tab to the lowest security setting. (A warning will appear, click ok.)**
 - **Select Apply, you'll need to close the browser and reopen it before these settings will take effect.**
 - **Click OK.**
7. If you have a VPN-VPN Gateway established between our sites, then you will not need VPN-Client software. The VPN-VPN Gateway sites that have been established are listed on https://aristotle.hosc.msfc.nasa.gov/IVODS/VPN_to_VPN_Sites_Established.html.
8. For instructions on obtaining and installing the Checkpoint VPN client, go to https://aristotle.hosc.msfc.nasa.gov/POIC_Page/SecureRemote.pdf
9. To begin using SecuRemote, Double-click on the IVoDS Gateway Icon.
(IF you do NOT have an "IVoDS Gateway" ICON as shown in the figure below, then you will need to create a new site per instructions listed below.)
 - a.) **Choose Sites>Create New>**
 - b.) **In the Name/IP space, enter foivods.hosc.msfc.nasa.gov and click "OK".**
 - c.) **Enter your VPN username and password and click "OK".**
10. You are now ready to run IVoDS. Double click the IVoDS icon located on your desktop (see figure 1 below) and it will take you to the IVoDS browser.

Figure 1



Ivods.lnk

If you experience any problems, please call the help desk at 256-544-5066 or email the help desk at <mailto:hsd@hosc.msfc.nasa.gov>